

# Principles of Surgery

James R. Hupp



## CHAPTER



### CHAPTER OUTLINE

DEVELOPING A SURGICAL DIAGNOSIS  
BASIC NECESSITIES FOR SURGERY  
ASEPTIC TECHNIQUE  
INCISIONS  
FLAP DESIGN  
    Prevention of Flap Necrosis  
    Prevention of Flap Dehiscence  
    Prevention of Flap Tearing

TISSUE HANDLING  
HEMOSTASIS  
    Means of Promoting Wound Hemostasis  
    Dead Space Management  
DECONTAMINATION AND DEBRIDEMENT  
EDEMA CONTROL  
PATIENT GENERAL HEALTH AND NUTRITION

Human tissues have genetically determined properties that make their responses to injury fairly predictable. Depending on this predictability, principles of surgery that help to optimize the wound-healing environment have evolved through time and through basic and clinical research. This chapter presents the principles of surgical practice that clinicians and investigators have found most successful.

#### DEVELOPING A SURGICAL DIAGNOSIS

Most of the important decisions concerning a maxillofacial surgical procedure should be made long before the administration of anesthesia. The decision to perform surgery should be the culmination of several diagnostic steps. In the analytic approach the surgeon first identifies the various signs and symptoms and relevant historical information; then, using available data and logical reasoning, the surgeon establishes the relationship between the individual problems.

The initial step in the presurgical evaluation is the collection of accurate and pertinent data. This is accomplished through patient interviews; physical, laboratory, and imaging examinations; and the use of consultants when necessary. Patient interviews and physical examinations should be performed in an unhurried, thoughtful fashion. The surgeon should not be willing to accept incomplete data, such as a poor-quality radiograph, especially when it is probable that additional data might change decisions concerning surgery.

For a good analysis, data must be organized into a form that allows for hypothesis testing; that is, the dentist should be able to consider a list of possible diseases and eliminate those unsupported by the data. By using this method, along with the knowledge of which diseases have a probability of being present, the surgeon is usually able to reach a decision about whether surgery is indicated.

Clinicians also must be thoughtful observers. Whenever a procedure is performed, they should note all aspects of its outcome to advance their surgical knowl-

edge and to improve future surgical results. This procedure should also be followed whenever a clinician is learning about a new technique. In addition, a clinician should practice evidence-based dentistry by evaluating the purported results of any new technique by weighing the scientific merit of studies used to investigate the technique. Frequently, scientific methods are violated by the unrecognized introduction of a placebo effect, observer bias, patient variability, or use of inadequate control groups.

## BASIC NECESSITIES FOR SURGERY

Little difference exists between the basic necessities required for oral surgery and those required for the proper performance of other aspects of dentistry. The two principal requirements are (1) adequate visibility and (2) assistance.

Although visibility may seem too obvious to mention as a requirement for performing surgery, clinicians often overlook it. Adequate visibility depends upon the following three factors: (1) adequate access, (2) adequate light, and (3) a surgical field free of excess blood and other fluids.

Adequate access not only requires the patient's ability to open the mouth widely, but it also may require surgically created exposure. Retraction of tissues away from the operative field provides much of the necessary access. (Proper retraction also protects tissues from being accidentally injured, for example, by cutting instruments.) Improved access is also gained by the creation of surgical flaps, which are discussed later in this chapter.

Adequate light is another obvious necessity for surgery. However, clinicians often forget that many surgical procedures place the surgeon or assistant in positions that block chair-based light sources. To correct this problem, the light source must continually be repositioned, or the surgeon or assistant must avoid obstructing the light or use a headlight.

A surgical field free of fluids is also necessary for adequate visibility. High-volume suctioning with a relatively small tip can quickly remove blood and other fluids from the field.

As in other types of dentistry, a properly trained assistant provides invaluable help during oral surgery. The assistant should be sufficiently familiar with the procedures being performed to anticipate the surgeon's needs. It is extremely difficult to perform good surgery with no or poor assistance.

## ASEPTIC TECHNIQUE

Aseptic technique includes minimizing wound contamination by pathogenic microbes. This important surgical principle is discussed in detail in Chapter 5.

## INCISIONS

Many oral and maxillofacial surgical procedures necessitate incisions. A few basic principles are important to remember when performing incisions.

The first principle is that a sharp blade of the proper size should be used. A sharp blade allows incisions to be made cleanly, without unnecessary damage caused by repeated strokes. The rate at which a blade dulls depends on the resistance of tissues through which the blade cuts. Bone and ligamental tissues dull blades more rapidly than does buccal mucosa. Therefore the surgeon should change blades whenever the knife does not seem to be incising easily.

The second principle is that a firm, continuous stroke should be used when incising. Repeated, tentative strokes increase both the amount of damaged tissue within a wound and the amount of bleeding, thereby impairing wound healing. Long, continuous strokes are preferred to short, interrupted ones (Fig. 3-1, *A*).

The third principle is that the surgeon should carefully avoid cutting vital structures when incising. No patient's microanatomy is exactly the same. Therefore to avoid unintentionally cutting large vessels or nerves, the surgeon must incise only deeply enough to define the next layer. Vessels can be more easily controlled before they are completely divided, and important nerves can usually be freed from adjacent tissue and retracted away from the area to be incised. In addition, when using a scalpel the surgeon's focus must remain on the blade to avoid accidentally cutting structures such as the lips when introducing and removing the blade to and from the mouth.

The fourth principle is that incisions through epithelial surfaces that the surgeon plans to reapproximate should be made with the blade held perpendicular to the epithelial surface. This angle produces squared wound edges that are both easier to reorient properly during suturing and less susceptible to necrosis of the wound edges as a result of ischemia (Fig. 3-1, *B*).


The fifth principle is that incisions in the oral cavity should be properly placed. It is more desirable to incise through attached gingiva and over healthy bone than through unattached gingiva and over unhealthy or missing bone. Properly placed incisions allow the wound margins to be sutured over intact, healthy bone that is at least a few millimeters away from the damaged bone, thereby providing support for the healing wound. Incisions placed near the teeth for extractions should be made in the gingival sulcus, unless the clinician feels it is necessary to excise the marginal gingiva or to leave the marginal gingiva untouched.

## FLAP DESIGN

Surgical flaps are made to gain surgical access to an area or to move tissue from one place to another. Several basic principles of flap design must be followed to prevent the complications of flap surgery: flap necrosis, dehiscence, and tearing.

### Prevention of Flap Necrosis

Flap necrosis can be prevented if the surgeon attends to four basic principles. First, the apex (tip) of a flap should never be wider than the base, unless a major artery is present in the base. Flaps should have sides that either run par-



**FIG. 3-1** A, Proper method of making incision using no. 15 scalpel blade. Note scalpel motion made by moving hand at wrist and not by moving entire forearm. B, When creating tissue layer that is to be sutured closed, blade should be kept perpendicular to tissue surface to create squared wound edges. Holding blade at any angle other than 90 degrees to tissue surface creates an oblique cut that is difficult to close properly and that compromises blood supply to the wound edge. (Modified from Clark HB jr. *Practical oral surgery*, ed 3, Philadelphia, 196S, Lea & Febiger.)

allel to each other or, preferably, converge moving from the base to the apex of the flap. Second, generally the length of a flap should be no more than twice the width of the base (Fig. 3-2, A-C). Strict adherence to this principle is less critical in the oral cavity, but in this location the length of the flap should never exceed the width. Third, when possible, an axial blood supply should be included in the base of the flap. For example, a flap in the palate should be based toward the greater palatine artery (see Fig. 3-2). Fourth, the base of flaps should not be excessively twisted, stretched, or grasped with anything that might damage vessels, because these maneuvers can compromise the blood supply feeding and draining the flap.

### Prevention of Flap Dehiscence

Flap margin dehiscence (separation) is prevented by approximating the edges of the flap over healthy bone, by gently handling the flap's edges, and by **not** placing the flap under tension. Dehiscence exposes underlying bone, producing pain, bone loss, and increased scarring.


### Prevention of Flap Tearing

Tearing of a flap is a common complication of the inexperienced surgeon who attempts to perform a procedure using a flap that provides insufficient access. Because a properly repaired long incision heals just as quickly as a short one, it is preferable to create a flap at the onset of surgery that is large enough for the surgeon to avoid

either tearing it or interrupting surgery to enlarge it. Envelope flaps are those created by incisions that produce a one-sided flap. An example is an incision made around the necks of several teeth to expose the alveolar bone without any vertical incisions. However, if an envelope flap does not provide sufficient access, another incision should be made to prevent it from tearing (Fig. 3-3). Vertical (oblique) releasing incisions should generally be placed one full tooth anterior to the area of any anticipated bone removal. The incision is generally started at the line angle of a tooth or in the adjacent interdental papilla and carried obliquely apically into the unattached gingiva. It is uncommon to need more than one releasing incision when using a flap to gain oral surgical access.

### TISSUE HANDLING

The difference between an acceptable and an excellent surgical outcome often rests on how the surgeon handles the tissues. The use of proper incision and flap design techniques plays a role; however, tissue also must be handled carefully. Excessive pulling or crushing, extremes of temperature, desiccation, or the use of unphysiologic chemicals easily damage tissue. Therefore the surgeon should use care whenever touching tissue. When tissue forceps are used, they should not be pinched together too tightly; rather, they should be used to delicately hold the tissue. When possible, toothed forceps or tissue hooks should be used to hold tissue (Fig. 3-4). In addition, tissue should not be overaggressively retracted to gain greater surgical access. This




**FIG. 3-2** A, Principles of flap design. In general, flap base dimension ( $x$ ) must not be less than height dimension ( $y$ ), and preferably flap should have  $x = 2y$ . B, When releasing, incision is used to reflect a two-sided flap; incision should be designed to maximize flap blood supply by leaving wide base. Design on left is *correct*; design on right is *incorrect*. C, When "buttonhole" occurs near free edge of flap, blood supply to flap tissue on side of hole away from flap base is compromised.

includes not pulling excessively on the cheeks or tongue during surgery. When bone is cut, copious amounts of irrigation should be used to decrease the amount of bone damage from heat. Soft tissues should also be protected from frictional heat or direct trauma from drilling equipment. Tissues should not be allowed to desiccate; open wounds should be frequently moistened or covered with a damp sponge. Finally, only physiologic substances should come in contact with living tissue. For example, tissue forceps used to place a specimen into formalin during a biopsy procedure should not be returned to the wound until any contaminating formalin is thoroughly removed. The surgeon who handles tissue gently is rewarded with grateful patients whose wounds heal with fewer complications.


## HEMOSTASIS

Prevention of excessive blood loss during surgery is important for preserving a patient's oxygen-carrying capacity. However, maintaining meticulous hemostasis during surgery is necessary for other important reasons. One is the decreased visibility that uncontrolled bleeding creates. Even high-volume suctioning cannot keep a surgical field completely dry, particularly in the well-vascularized oral and maxillofacial regions. Another problem bleeding causes is the formation of hematomas. Hematomas place pressure on wounds, decreasing vascularity; they increase tension on the wound edges; and they act as culture media, potentiating the development of a wound infection.





**FIG. 3-3** Three types of properly designed oral soft tissue flaps. A, Horizontal and single vertical incisions used to create two-sided flap. B, Horizontal and two vertical incisions used to create three-sided flap. C, Single horizontal incision used to create single-sided (envelope) flap.



**FIG. 3-4** Instruments used to minimize damage while holding soft tissue. *Top*, finely toothed tissue forceps (pickups); *bottom*, soft tissue (skin) hook.


### Means of Promoting Wound Hemostasis

Wound hemostasis can be obtained in five ways. The first is by assisting natural hemostatic mechanisms. This is usually accomplished by either using a fabric sponge to place pressure on bleeding vessels or placing a hemostat on a vessel. Both methods cause stasis of blood in vessels, which promotes coagulation. A few small vessels generally require pressure for only 20 to 30 seconds, whereas larger vessels require 5 to 10 minutes of continuous pressure. The surgeon and assistants should dab rather than wipe the wound with sponges to remove extravasated blood. Wiping is more likely to reopen vessels that are already plugged by clotted blood.

A second means of obtaining hemostasis is by the use of heat to cause the ends of cut vessels to fuse closed (thermal coagulation). Heat is usually applied through an electrical current that the surgeon concentrates on the bleeding vessel by holding the vessel with a metal instrument, such as a hemostat, or by touching the vessel directly with an electrocautery tip. Three conditions should be created for proper use of thermal coagulation. First, the patient must be grounded, to allow the current to enter the body. Second, the cautery tip and any metal instrument the cautery tip contacts cannot touch the patient at any point other than the site of the bleeding vessel. Otherwise the current may follow an undesirable path and create a burn. The third necessity for thermal coagulation is the removal of any blood or fluid that has accumulated around the vessel to be cauterized. Fluid acts as an energy sump and thus prevents a sufficient amount of heat from reaching the vessel to cause closure.

The third means of providing surgical hemostasis is by suture ligation. If a sizable vessel is already severed, each end is grasped with a hemostat. The surgeon then ties a nonabsorbable suture around the vessel. If a vessel can be dissected free of surrounding connective tissue before it is cut, two hemostats can be placed on the vessel, with enough space left between them to cut the vessel. Once the vessel is severed, sutures are tied around each end and the hemostats removed.

The fourth means of gaining hemostasis is by placement of a pressure dressing over the wound. This creates pressure on the small vessels that were cut, promoting coagula-



**FIG. 3-5** Example of nonsuction drain. This is a Penrose drain and is made of flexible, rubberized material that can be placed into wound during closure or after incision and drainage of abscess to prevent premature sealing of wound before blood or pus collections can drain to surface. Draining material runs both along and through Penrose drain. In this illustration, suture has been tied to drain and drain is ready for insertion into wound. Needled end of suture will be used to attach drain to wound edge to hold drain in place.

tion. Care must be taken not to apply so much pressure as to compromise wound vascularity. Most bleeding from dentoalveolar surgery can be controlled by this means.

The fifth method of promoting hemostasis is by placing vasoconstrictive substances, such as epinephrine, in the wound or by applying procoagulants, such as commercial thrombin or collagen, on the wound. Epinephrine serves as a vasoconstrictor most effectively when placed in the site of desired vasoconstriction at least 7 minutes before surgery begins.

### Dead Space Management

Dead space in a wound is any area that remains devoid of tissue after closure of the wound. Dead space is created by either removing tissue in the depths of a wound or by not reapproximating all tissue planes during closure. Dead space in a wound usually fills with blood, which creates a hematoma with a high potential for infection.

Dead space can be eliminated in four ways. The first is by suturing tissue planes together to minimize the postoperative void. A second method is to place a pressure dressing over the repaired wound. The dressing compresses tissue planes together until they are either bound by fibrin or pressed together by surgical edema (or both). This usually takes about 12 to 18 hours. The third way to eliminate dead space is to place packing into the void until bleeding has stopped and then remove the packing. This technique is usually used when the surgeon is unable to tack tissue together or to place pressure dressings (e.g., when bony cavities are present). The packing material is usually impregnated with an antibacterial medication to lessen the chance of infection. The fourth means of preventing dead space is through the use of drains, either by themselves or in addition to pressure dressings. Suction drains continually remove any blood

that accumulates in a wound until the bleeding stops and the tissues bind together and eliminate dead space. Nonsuction drains allow any bleeding to drain to the surface rather than to form a hematoma (Fig. 3-5).

### DECONTAMINATION AND DEBRIDEMENT

Bacteria invariably contaminate all wounds that are open to the external or oral environment. Because the risk of infection rises with the increased size of an inoculum, one way to lessen the chance of wound infection is to decrease the bacterial count. This is easily accomplished by repeatedly irrigating the wound during surgery and closure. Irrigation dislodges bacteria and other foreign materials and rinses them out of the wound. Irrigation can be achieved by forcing *large volumes* of fluid under pressure on the wound. Although solutions containing antibiotics can be used, most surgeons simply use sterile saline or sterile water.

Wound debridement is the careful removal from injured tissue of necrotic, foreign, and severely ischemic material that would impede wound healing. In general, debridement is used only during care of traumatically incurred wounds or for severe tissue damage caused by a pathologic condition.

### EDEMA CONTROL

Edema occurs after surgery as a result of tissue injury. Edema is an accumulation of fluid in the interstitial space because of transudation from damaged vessels and lymphatic obstruction by fibrin. Two variables help determine the degree of postsurgical edema. First, the greater the amount of tissue injury, the greater the amount of edema. Second, the more loose connective tissue that is contained in the injured region, the more edema is present. For example, attached gingiva has little loose connective tissue, so it exhibits little tendency toward edema; however, the lips and floor of the mouth contain large amounts of loose connective tissue and can swell significantly.

The dentist can control the amount of postsurgical edema by performing surgery in a manner that minimizes tissue damage. Some believe that ice applied to a freshly wounded area decreases vascularity and thereby diminishes transudation. However, no controlled study has verified the effectiveness of this practice. Patient positioning in the early postoperative period is also used to decrease edema by having the patient try to keep the head elevated above the rest of the body as much as possible during the first few postoperative days. Short-term, high-dose systemic corticosteroids can be administered to the patient and have an impressive ability to lessen inflammation and transudation (and thus edema). However, corticosteroids are useful for edema control only if administration is begun before tissue is damaged.

### PATIENT GENERAL HEALTH AND NUTRITION

Proper wound healing depends on a patient's ability to resist infection, to provide essential nutrients for use as building materials, and to carry out reparative cellular

processes. Numerous medical conditions impair a patient's ability to resist infection and heal wounds. These include conditions that establish a catabolic state of metabolism, that impede oxygen or nutrient delivery to tissues, and that require administration of drugs or physical agents that interfere with immunologic or wound-healing cells. Examples of diseases that induce a catabolic metabolic state include poorly controlled insulin-dependent diabetes mellitus, end-stage renal or hepatic disease, and malignant diseases. Conditions that interfere with the delivery of oxygen or nutrients to wounded tissues include severe chronic obstructive pulmonary disease (COPD), poorly compensated congestive heart failure (hypertrophic cardiomyopathy), and drug addictions, such as ethanolism. Diseases requiring the administration of drugs that interfere with host defenses or wound-healing capabilities include autoimmune dis-

eases for which long-term corticosteroid therapy is given and malignancies for which cytotoxic agents and irradiation are used.

The surgeon can help improve the patient's chances of having normal healing of an elective surgical wound by evaluating and optimizing the patient's general health status before surgery. For malnourished patients, this includes improving the nutritional status so that the patient is in a positive nitrogen balance and an anabolic metabolic state.

#### **BIBLIOGRAPHY**

Cohen DC, Diegelmann RF, Lindblad WJ: *Wound healing: biochemical and clinical aspects*, Philadelphia, 1992, WB Saunders.

Leaper DJ, Harding KG: *Wounds: biology and management*, Oxford, 1998, Oxford University Press.

DropBooks